modphpcms Reference Manual

CVS >= 20040608

Generated by Doxygen 1.2.18

Wed Jun 9 03:38:16 2004

Contents

1 modPHPcms developer's documentation **1**

2 modphpcms File Index **3**

2.1 modphpcms File List 3

3 modphpcms Page Index **5**

3.1 modphpcms Related Pages 5

4 modphpcms File Documentation **7**

4.1 activate.inc.php File Reference 7

4.2 base_page.inc.php File Reference 8

4.3 base_page.php File Reference 10

4.4 basic_page.inc.php File Reference 12

4.5 basic_page.php File Reference 13

4.6 config.inc.php File Reference 14

4.7 copyright.php File Reference 15

4.8 db_mysql.php File Reference 16

4.9 dbcleanup.php File Reference 19

4.10 htmlparse.inc.php File Reference 20

4.11 logo.php File Reference 22

4.12 meta_generator.php File Reference 24

4.13 modfuncs.inc.php File Reference 25

4.14 page.php File Reference 28

4.15 pageend.inc.php File Reference 29

4.16 pagestart.inc.php File Reference 30

4.17 secureimage.php File Reference 31

4.18 stats.inc.php File Reference 33

4.19 stats.php File Reference 34

4.20 stats_text.php File Reference 35

4.21 style.php File Reference 36
4.22 template.php File Reference 37

5 modphpcms Page Documentation **39**
5.1 Todo List 39

Chapter 1

modPHPcms developer's documentation

1.0.1 Introduction

This documentation is lifted by doxygen from the modphpcms source. This documentation is embedded in the source as specially structured comments. This text can be found in **page.php**.

1.0.2 What is this?

This documentation details every function that is part of the modphpcms API, both internal and for the use of module developers. It should give descriptions of parameters when they are not obvious, and also return values.

Chapter 2

modphpcms File Index

2.1 modphpcms File List

Here is a list of all files with brief descriptions:

activate.inc.php . . . 7
base_page.inc.php (Helper functions for the base_page module) . . . 8
base_page.php (The core layout engine) . . . 10
basic_page.inc.php . . . 12
basic_page.php . . . 13
config.inc.php (This file contains the configuration information) . . . 14
copyright.php . . . 15
db_mysql.php . . . 16
dbcleanup.php . . . 19
htmlparse.inc.php (Contains functions for parsing HTML) . . . 20
logo.php . . . 22
meta_generator.php . . . 24
modfuncs.inc.php (This file contains helper functions used by modules) . . . 25
page.php (This file is the main interface of modphpcms) . . . 28
pageend.inc.php (Included at the end of every page) . . . 29
pagestart.inc.php (Included at the start of every page) . . . 30
secureimage.php . . . 31
stats.inc.php . . . 33
stats.php . . . 34
stats_text.php . . . 35
style.php . . . 36
template.php . . . 37

Chapter 3

modphpcms Page Index

3.1 modphpcms Related Pages

Here is a list of all related documentation pages:

Todo List 39

Chapter 4

modphpcms File Documentation

4.1 activate.inc.php File Reference

Functions

- **style_default_activate** ()

4.1.1 Function Documentation

4.1.1.1 style_default_activate ()

Definition at line 2 of file activate.inc.php.

References set_entry().

4.2 base_page.inc.php File Reference

Helper functions for the base_page module.

Functions

- **Ibase_page_getColSpan** ($cell)
  Gets the column span of a given cell.
- **Ibase_page_getRowSpan** ($cell)
  Gets the row span of a given cell.
- **Ibase_page_doShowData** ($cell)
  Works out if data should be shown.

4.2.1 Detailed Description

Helper functions for the base_page module.

Definition in file **base_page.inc.php**.

4.2.2 Function Documentation

4.2.2.1 Ibase_page_doShowData ($ *cell*)

Works out if data should be shown.

Parameters:
cell The name of the cell.

Returns:
true/false.

Definition at line 154 of file base_page.inc.php.

References get_entry(), Ibase_page_getColSpan(), and Ibase_page_getRowSpan().

Referenced by get_page().

4.2.2.2 Ibase_page_getColSpan ($ *cell*)

Gets the column span of a given cell.

Parameters:
cell The name of the cell.

Returns:
Integer, >= 0

Definition at line 15 of file base_page.inc.php.

References get_entry(), and Ibase_page_getRowSpan().

Referenced by get_page(), and Ibase_page_doShowData().

4.2.2.3 Ibase_page_getRowSpan ($ *cell*)

Gets the row span of a given cell.

m $cell The name of the cell.

Returns:
Integer, >= 0

Definition at line 91 of file base_page.inc.php.

References get_entry().

Referenced by get_page(), Ibase_page_doShowData(), and Ibase_page_getColSpan().

4.3 base_page.php File Reference

The core layout engine.

Functions

- **base_page_install** ()

  Installs the base_page module.

- **base_page_uninstall** ($preserve_data)

  Uninstalls the base_page module.

- **get_page** ()

  Displays the requested page.

Variables

- include includes base_page inc **php**

4.3.1 Detailed Description

The core layout engine.

This file generates the most of the layout (structural tables, etc), and calls the appropriate hooks in each table cell.

Todo:
This code is not really modular - needs fixing.

Definition in file **base_page.php**.

4.3.2 Function Documentation

4.3.2.1 base_page_install ()

Installs the base_page module.

This is called by the main installation routine - it adds the module to the database.

Returns:
Nothing.

Definition at line 22 of file base_page.php.

References get_entry(), ListAdd(), module_installed(), set_entry(), and set_module_info().

4.3.2.2 base_page_uninstall ($ *preserve_data*)

Uninstalls the base_page module.

You *really* shouldn't call this unless you know exactly what you are doing - base_page is a core module, and as such is required for modphpcms to function.

Parameters:
preserve_data true/false

Returns:
Nothing.

Definition at line 72 of file base_page.php.

References delete_entry(), delete_module(), get_entry(), ListDel(), and set_entry().

4.3.2.3 get_page ()

Displays the requested page.

This will draw the main page body (a 3x3 grid), which can contain whatever is chosen by the user (and a module exists for), such as website titles, page titles, logos, navigation bars, hit counters, adverts, etc.

The middle-centre box deals with the content.

Returns:
Nothing.

Definition at line 119 of file base_page.php.

References CallHooks(), get_entry(), Ibase_page_doShowData(), Ibase_page_getColSpan(), and Ibase_page_getRowSpan().

4.3.3 Variable Documentation

4.3.3.1 include includes modfuncs inc php

Definition at line 5 of file style.php.

4.4 basic_page.inc.php File Reference

Functions

- **basic_page_DoSummary** ($pid)
- **Ibasic_page_cmpID** ($a,$b)

4.4.1 Function Documentation

4.4.1.1 basic_page_DoSummary ($ *pid*)

Definition at line 4 of file basic_page.inc.php.

References CallHooks(), get_entry(), get_field(), RemoveHTML(), and textToXHTML().

4.4.1.2 Ibasic_page_cmpID ($ *a*, $ *b*)

Definition at line 68 of file basic_page.inc.php.

Referenced by basic_page_content().

4.5 basic_page.php File Reference

Functions

- **basic_page_install** ()
- **basic_page_uninstall** ($preserve_data)
- **basic_page_content** ()

Variables

- include includes basic_page inc **php**

4.5.1 Function Documentation

4.5.1.1 basic_page_content ()

Definition at line 48 of file basic_page.php.

References CallHooks(), get_array2(), get_entry(), get_field(), get_field2(), get_module_info(), get_reccount(), Ibasic_page_cmpID(), php, RemoveHTML(), and textToXHTML().

4.5.1.2 basic_page_install ()

Definition at line 5 of file basic_page.php.

References get_entry(), ListAdd(), module_installed(), set_entry(), and set_module_info().

4.5.1.3 basic_page_uninstall ($ *preserve_data*)

Definition at line 28 of file basic_page.php.

References delete_entry(), delete_module(), get_entry(), ListDel(), and set_entry().

4.5.2 Variable Documentation

4.5.2.1 include includes basic_page inc php

Definition at line 3 of file basic_page.php.

Referenced by basic_page_content().

4.6 config.inc.php File Reference

This file contains the configuration information.

4.6.1 Detailed Description

This file contains the configuration information.

This file contains installation-specific configuration information, such as database configuration information.

Definition in file **config.inc.php**.

4.7 copyright.php File Reference

Functions

- **copyright_install** ()
- **copyright_uninstall** ($preserve_data)
- **copyright_at_bottom** ()

4.7.1 Function Documentation

4.7.1.1 copyright_at_bottom ()

Definition at line 37 of file copyright.php.

References get_entry(), and get_module_info().

4.7.1.2 copyright_install ()

Definition at line 4 of file copyright.php.

References get_entry(), ListAdd(), module_installed(), set_entry(), and set_module_info().

4.7.1.3 copyright_uninstall ($ *preserve_data*)

Definition at line 24 of file copyright.php.

References delete_entry(), delete_module(), get_entry(), ListDel(), and set_entry().

4.8 db_mysql.php File Reference

Functions

- **create_entry_table** ($name)
- **drop_table** ($name)
- **delete_entry** ($table,$key)
- **set_entry** ($table,$key,$value)
- **get_entry** ($table,$key)
- **get_module_list** ()
- **get_module_info** ($name)
- **set_module_info** ($info)
- **delete_module** ($name)
- **optimize_table** ($name)
- **add_field** ($table,$field,$type)
- **drop_field** ($table,$field)
- **get_array** ($table,$searchfield,$searchvalue)
- **set_field** ($table,$searchfield,$searchvalue,$field,$value)
- **get_field** ($table,$searchfield,$searchvalue,$field)
- **get_reccount** ($table)
- **get_array2** ($table,$recnum)
- **get_field2** ($table,$field,$recnum)

4.8.1 Function Documentation

4.8.1.1 add_field ($ *table*, $ *field*, $ *type*)

Definition at line 194 of file db_mysql.php.

Referenced by stats_install().

4.8.1.2 create_entry_table ($ *name*)

Definition at line 3 of file db_mysql.php.

Referenced by stats_install().

4.8.1.3 delete_entry ($ *table*, $ *key*)

Definition at line 41 of file db_mysql.php.

Referenced by base_page_uninstall(), basic_page_uninstall(), copyright_uninstall(), dbcleanup_uninstall(), logo_uninstall(), and meta_generator_uninstall().

4.8.1.4 delete_module ($ *name*)

Definition at line 156 of file db_mysql.php.

Referenced by base_page_uninstall(), basic_page_uninstall(), copyright_uninstall(), dbcleanup_uninstall(), logo_uninstall(), meta_generator_uninstall(), MODULE_NAME_uninstall(), stats_text_uninstall(), and stats_uninstall().

4.8.1.5 drop_field ($ *table*, $ *field*)

Definition at line 212 of file db_mysql.php.

Referenced by stats_uninstall().

4.8.1.6 drop_table ($ *name*)

Definition at line 23 of file db_mysql.php.

Referenced by stats_uninstall().

4.8.1.7 get_array ($ *table*, $ *searchfield*, $ *searchvalue*)

Definition at line 231 of file db_mysql.php.

Referenced by get_module_info().

4.8.1.8 get_array2 ($ *table*, $ *recnum*)

Definition at line 320 of file db_mysql.php.

Referenced by basic_page_content().

4.8.1.9 get_entry ($ *table*, $ *key*)

Definition at line 66 of file db_mysql.php.

References get_field().

Referenced by base_page_install(), base_page_uninstall(), basic_page_content(), basic_page_DoSummary(), basic_page_install(), basic_page_uninstall(), CallHooks(), copyright_at_bottom(), copyright_install(), copyright_uninstall(), dbcleanup_install(), dbcleanup_page_sent(), dbcleanup_uninstall(), get_page(), Ibase_page_doShowData(), Ibase_page_getColSpan(), Ibase_page_getRowSpan(), Ilogo_doLogo(), Iparse_markup(), is_standard_page(), Istats_getCount(), Istats_UIRH(), logo_install(), logo_uninstall(), meta_generator_in_head(), meta_generator_install(), meta_generator_uninstall(), module_installed(), MODULE_NAME_install(), MODULE_NAME_uninstall(), stats_install(), stats_on_request(), stats_text_DoStats(), stats_text_install(), stats_text_uninstall(), and stats_uninstall().

4.8.1.10 get_field ($ *table*, $ *searchfield*, $ *searchvalue*, $ *field*)

Definition at line 292 of file db_mysql.php.

Referenced by basic_page_content(), basic_page_DoSummary(), get_entry(), and stats_on_request().

4.8.1.11 get_field2 ($ *table*, $ *field*, $ *recnum*)

Definition at line 349 of file db_mysql.php.

Referenced by basic_page_content(), and Istats_totalCount().

4.8.1.12 get_module_info ($ *name*)

Definition at line 103 of file db_mysql.php.

References get_array().

Referenced by basic_page_content(), copyright_at_bottom(), dbcleanup_page_sent(), Ilogo_doLogo(), meta_generator_in_head(), MODULE_NAME_some_hook(), stats_on_request(), and stats_text_DoStats().

4.8.1.13 get_module_list ()

Definition at line 72 of file db_mysql.php.

4.8.1.14 get_reccount ($ *table*)

Definition at line 299 of file db_mysql.php.

Referenced by basic_page_content(), and Istats_totalCount().

4.8.1.15 optimize_table ($ *name*)

Definition at line 176 of file db_mysql.php.

Referenced by dbcleanup_page_sent().

4.8.1.16 set_entry ($ *table*, $ *key*, $ *value*)

Definition at line 60 of file db_mysql.php.

References set_field().

Referenced by base_page_install(), base_page_uninstall(), basic_page_install(), basic_page_uninstall(), copyright_install(), copyright_uninstall(), dbcleanup_install(), dbcleanup_uninstall(), Iparse_markup(), Istats_UIRH(), logo_install(), logo_uninstall(), meta_generator_install(), meta_generator_uninstall(), MODULE_NAME_install(), MODULE_NAME_uninstall(), stats_install(), stats_on_request(), stats_text_install(), stats_text_uninstall(), stats_uninstall(), and style_default_activate().

4.8.1.17 set_field ($ *table*, $ *searchfield*, $ *searchvalue*, $ *field*, $ *value*)

Definition at line 255 of file db_mysql.php.

Referenced by set_entry(), and stats_on_request().

4.8.1.18 set_module_info ($ *info*)

Definition at line 109 of file db_mysql.php.

Referenced by base_page_install(), basic_page_install(), copyright_install(), dbcleanup_install(), logo_install(), meta_generator_install(), MODULE_NAME_install(), stats_install(), and stats_text_install().

4.9 dbcleanup.php File Reference

Functions

- **dbcleanup_install** ()
- **dbcleanup_uninstall** ($preserve_data)
- **dbcleanup_page_sent** ()

4.9.1 Function Documentation

4.9.1.1 dbcleanup_install ()

Definition at line 4 of file dbcleanup.php.

References get_entry(), ListAdd(), module_installed(), set_entry(), and set_module_info().

4.9.1.2 dbcleanup_page_sent ()

Definition at line 43 of file dbcleanup.php.

References get_entry(), get_module_info(), and optimize_table().

4.9.1.3 dbcleanup_uninstall ($ *preserve_data*)

Definition at line 30 of file dbcleanup.php.

References delete_entry(), delete_module(), get_entry(), ListDel(), and set_entry().

4.10 htmlparse.inc.php File Reference

Contains functions for parsing HTML.

Functions

- **textToXHTML** (&$**text**,$allowIMG,$NoTags=FALSE)

  Converts properly formatted text to XHTML.

- **RemoveHTML** (&$**text**)

  Removes HTML from the text.

- **Iparse_markup** (&$**text**,$allowIMG,$NoTags=FALSE)

  Parses square-bracket tags.

4.10.1 Detailed Description

Contains functions for parsing HTML.

This file contains several helper functions for handling articles.

Definition in file **htmlparse.inc.php**.

4.10.2 Function Documentation

4.10.2.1 Iparse_markup (&$ *text*, $ *allowIMG*, $ *NoTags* = FALSE)

Parses square-bracket tags.

This will replace all the square-bracket tags with their XHTML equivalents. This is currently the only place where changes need to be made if you want to create a new tag.

This function is for internal use only - you are probably interested in **textToXHTML** (p. 21). The paramaters are not documented, because they may change frequently, and are not part of the API.

Definition at line 62 of file htmlparse.inc.php.

References get_entry(), set_entry(), and text.

Referenced by textToXHTML().

4.10.2.2 RemoveHTML (&$ *text*)

Removes HTML from the text.

This should be used when submitting an article - all formatting should be done with square brackets, therefore it's safe to assume that angle brackets are meant to be mathematical "less than" and "greater than" signs.

Parameters:

& $text The text to be stripped, by reference.

Returns:
Nothing.

Definition at line 45 of file htmlparse.inc.php.

References text.

Referenced by basic_page_content(), and basic_page_DoSummary().

4.10.2.3 textToXHTML (&$ *text*, $ *allowIMG*, $ *NoTags* = FALSE)

Converts properly formatted text to XHTML.

The text should be formatted with tags like "[b]some bold text[/b]". It will not check for valid XHTML, that should be done elsewhere.

Todo:
Define where XHTML checking should happen - probably on submitting a page.

Parameters:
& $text This is a string, passed by reference, to convert to XHTML

allowIMG This is a boolean, telling modphpcms if it should replace replace images with a textual placeholder

NoTags This tells modphpmcs if it should strip all tags from the text.

Returns:
Nothing.

Definition at line 24 of file htmlparse.inc.php.

References Iparse_markup(), and text.

Referenced by basic_page_content(), and basic_page_DoSummary().

4.11 logo.php File Reference

Functions

- **logo_install** ()
- **logo_uninstall** ($preserve_data)
- **logo_tl_cell** ()
- **logo_tr_cell** ()
- **logo_bl_cell** ()
- **logo_br_cell** ()
- **Ilogo_doLogo** ($cell)

4.11.1 Function Documentation

4.11.1.1 Ilogo_doLogo ($ *cell*)

Definition at line 88 of file logo.php.

References get_entry(), and get_module_info().

Referenced by logo_bl_cell(), logo_br_cell(), logo_tl_cell(), and logo_tr_cell().

4.11.1.2 logo_bl_cell ()

Definition at line 79 of file logo.php.

References Ilogo_doLogo().

4.11.1.3 logo_br_cell ()

Definition at line 83 of file logo.php.

References Ilogo_doLogo().

4.11.1.4 logo_install ()

Definition at line 4 of file logo.php.

References get_entry(), ListAdd(), module_installed(), set_entry(), and set_module_info().

4.11.1.5 logo_tl_cell ()

Definition at line 71 of file logo.php.

References Ilogo_doLogo().

4.11.1.6 logo_tr_cell ()

Definition at line 75 of file logo.php.

References Ilogo_doLogo().

4.11.1.7 logo_uninstall ($ *preserve_data*)

Definition at line 39 of file logo.php.

References delete_entry(), delete_module(), get_entry(), ListDel(), and set_entry().

4.12 meta_generator.php File Reference

Functions

- **meta_generator_install** ()
- **meta_generator_uninstall** ($preserve_data)
- **meta_generator_in_head** ()

4.12.1 Function Documentation

4.12.1.1 meta_generator_in_head ()

Definition at line 36 of file meta_generator.php.

References get_entry(), and get_module_info().

4.12.1.2 meta_generator_install ()

Definition at line 4 of file meta_generator.php.

References get_entry(), ListAdd(), module_installed(), set_entry(), and set_module_info().

4.12.1.3 meta_generator_uninstall ($ *preserve_data*)

Definition at line 23 of file meta_generator.php.

References delete_entry(), delete_module(), get_entry(), ListDel(), and set_entry().

4.13 modfuncs.inc.php File Reference

This file contains helper functions used by modules.

Functions

- **ListAdd** ($needle,&$haystack)
  Adds an item to a list.
- **ListDel** ($needle,&$haystack)
  Removes an item from a list.
- **CallHooks** ()
  Calls all modules which have added themselves to a given hook.
- **get_option** ($haystack,$needle)
  Get a given entry from a list.
- **set_option** (&$haystack,$needle,$value)
  Sets an entry in a list.
- **is_standard_page** ()
  Checks if the requested page is a "normal" page.
- **module_installed** ()
  To be called whenever a module is (un)installed.

4.13.1 Detailed Description

This file contains helper functions used by modules.

This includes several functions which modules and the module subsystem should use, such as the hook system, and the list manipulation system.

Currently a list is stored as a serialize'd array, suitable for storing in a database directly, however this may change, so these functions should be used.

Definition in file **modfuncs.inc.php**.

4.13.2 Function Documentation

4.13.2.1 CallHooks ()

Calls all modules which have added themselves to a given hook.

This function takes a variable length argument list - only the first argument is required, which is the name of the hook to call. The others are used if a certain hook needs additional parameters to be passed onto the called modules.

Parameters:
hookname The name of the hook to call.

... Parameters to pass on to the called modules.

Returns:
Nothing.

Definition at line 65 of file modfuncs.inc.php.

References get_entry().

Referenced by basic_page_content(), basic_page_DoSummary(), get_page(), and stats_tr_cell().

4.13.2.2 get_option ($ *haystack*, $ *needle*)

Get a given entry from a list.

Parameters:
haystack The list to search in.

needle The value to search for.

Returns:
The value of the entry in the list, if it exists, otherwise an empty string ("").

Definition at line 93 of file modfuncs.inc.php.

Referenced by Istats_getCount(), and stats_text_DoStats().

4.13.2.3 is_standard_page ()

Checks if the requested page is a "normal" page.

Returns:
true or false

Definition at line 127 of file modfuncs.inc.php.

References get_entry().

4.13.2.4 ListAdd ($ *needle*, &$ *haystack*)

Adds an item to a list.

Parameters:
needle The item to be added to the list.

& $haystack The list.

Returns:
Nothing.

Definition at line 23 of file modfuncs.inc.php.

Referenced by base_page_install(), basic_page_install(), copyright_install(), dbcleanup_install(), logo_install(), meta_generator_install(), MODULE_NAME_install(), stats_install(), and stats_text_install().

4.13.2.5 ListDel ($ *needle*, &$ *haystack*)

Removes an item from a list.

Parameters:

needle The item to be removed from the list.

& $haystack The list.

Returns:

Nothing.

Definition at line 41 of file modfuncs.inc.php.

Referenced by base_page_uninstall(), basic_page_uninstall(), copyright_uninstall(), dbcleanup_uninstall(), Istats_UIRH(), logo_uninstall(), meta_generator_uninstall(), MODULE_NAME_uninstall(), stats_text_uninstall(), and stats_uninstall().

4.13.2.6 module_installed ()

To be called whenever a module is (un)installed.

This contains functions which should be called whenever anything serious changes in the user's configuration of modphpcms. It will:

- Re-activate the user's currently selected style.

Returns:

Nothing.

Definition at line 151 of file modfuncs.inc.php.

References get_entry().

Referenced by base_page_install(), basic_page_install(), copyright_install(), dbcleanup_install(), logo_install(), meta_generator_install(), MODULE_NAME_install(), stats_install(), and stats_text_install().

4.13.2.7 set_option (&$ *haystack*, $ *needle*, $ *value*)

Sets an entry in a list.

This will set an entry in a list, creating the list and entry if neccessary.

Parameters:

& $haystack The list to set the entry in.

needle The identifier in the list.

value The value to set the entry to.

Returns:

Nothing.

Definition at line 113 of file modfuncs.inc.php.

4.14 page.php File Reference

This file is the main interface of modphpcms.

Variables

- include includes config inc **php**

4.14.1 Detailed Description

This file is the main interface of modphpcms.

This is the file that is requested by the browser when it wants a page. It will include the headers and footers, load the modules, and call the appropriate hooks to generate the content.

Definition in file **page.php**.

4.14.2 Variable Documentation

4.14.2.1 include includes pageend inc php

Definition at line 69 of file page.php.

4.15 pageend.inc.php File Reference

Included at the end of every page.

4.15.1 Detailed Description

Included at the end of every page.

This merely closes the body and html tags, and calls the "at_bottom" hook.

Definition in file **pageend.inc.php**.

4.16 pagestart.inc.php File Reference

Included at the start of every page.

4.16.1 Detailed Description

Included at the start of every page.

This will handle basics:

- Sending the appropriate mime-type for the browser ("application/xhtml+xml" or "text/html")
- The xml declaration and DOCTYPE tag
- Showing a warning if debugmode is enabled
- Showing a warning if install.php exists

Definition in file **pagestart.inc.php**.

4.17 secureimage.php File Reference

Functions

- **GetColor** (&$img)
- **MakeImage** ($letter)
- **HideImage** (&$img,$**hidelevel**)

Variables

- **text** = "alphabet"
- **hidelevel** = 5
- **outimg** = imagecreatetruecolor(50 * strlen($**text**), 50)

4.17.1 Function Documentation

4.17.1.1 GetColor (&$ *img*)

Definition at line 6 of file secureimage.php.

Referenced by HideImage(), and MakeImage().

4.17.1.2 HideImage (&$ *img*, $ *hidelevel*)

Definition at line 22 of file secureimage.php.

References GetColor(), and hidelevel.

4.17.1.3 MakeImage ($ *letter*)

Definition at line 12 of file secureimage.php.

References GetColor().

4.17.2 Variable Documentation

4.17.2.1 hidelevel = 5

Definition at line 4 of file secureimage.php.

Referenced by HideImage().

4.17.2.2 outimg = imagecreatetruecolor(50 * strlen($text), 50)

Definition at line 69 of file secureimage.php.

4.17.2.3 text = "alphabet"

Definition at line 3 of file secureimage.php.

Referenced by Iparse_markup(), Istats_reallyIE(), RemoveHTML(), stats_install(), stats_text_DoStats(), stats_text_install(), and textToXHTML().

4.18 stats.inc.php File Reference

Functions

- **Istats_reallyIE** ()
- **Istats_UIRH** ($cell)
- **Istats_totalCount** ()
- **Istats_getCount** ($id)

4.18.1 Function Documentation

4.18.1.1 Istats_getCount ($ *id*)

Definition at line 46 of file stats.inc.php.

References get_entry(), get_option(), and Istats_totalCount().

Referenced by stats_text_DoStats().

4.18.1.2 Istats_reallyIE ()

Definition at line 2 of file stats.inc.php.

References text.

Referenced by stats_on_request().

4.18.1.3 Istats_totalCount ()

Definition at line 34 of file stats.inc.php.

References get_field2(), and get_reccount().

Referenced by Istats_getCount().

4.18.1.4 Istats_UIRH ($ *cell*)

Definition at line 26 of file stats.inc.php.

References get_entry(), ListDel(), and set_entry().

4.19 stats.php File Reference

Functions

- **stats_install** ()
- **stats_uninstall** ($preserve_data)
- **stats_on_request** ()
- **stats_tr_cell** ()

Variables

- include includes stats inc **php**

4.19.1 Function Documentation

4.19.1.1 stats_install ()

Definition at line 6 of file stats.php.

References add_field(), create_entry_table(), get_entry(), ListAdd(), module_installed(), set_entry(), set_module_info(), and text.

4.19.1.2 stats_on_request ()

Definition at line 78 of file stats.php.

References get_entry(), get_field(), get_module_info(), Istats_reallyIE(), set_entry(), and set_field().

4.19.1.3 stats_tr_cell ()

Definition at line 137 of file stats.php.

References CallHooks().

4.19.1.4 stats_uninstall ($ *preserve_data*)

Definition at line 46 of file stats.php.

References delete_module(), drop_field(), drop_table(), get_entry(), ListDel(), and set_entry().

4.19.2 Variable Documentation

4.19.2.1 include includes stats inc php

Definition at line 4 of file stats.php.

4.20 stats_text.php File Reference

Functions

- **stats_text_install** ()
- **stats_text_uninstall** ($preserve_data)
- **stats_text_DoStats** ($id)

4.20.1 Function Documentation

4.20.1.1 stats_text_DoStats ($ *id*)

Definition at line 31 of file stats_text.php.

References get_entry(), get_module_info(), get_option(), Istats_getCount(), and text.

4.20.1.2 stats_text_install ()

Definition at line 4 of file stats_text.php.

References get_entry(), ListAdd(), module_installed(), set_entry(), set_module_info(), and text.

4.20.1.3 stats_text_uninstall ($ *preserve_data*)

Definition at line 21 of file stats_text.php.

References delete_module(), get_entry(), ListDel(), and set_entry().

4.21 style.php File Reference

Variables

- include includes config inc **php**

4.21.1 Variable Documentation

4.21.1.1 include includes modfuncs inc php

Definition at line 5 of file style.php.

4.22 template.php File Reference

Functions

- **MODULE_NAME_install** ()
- **MODULE_NAME_uninstall** ($preserve_data)
- **MODULE_NAME_some_hook** ()

4.22.1 Function Documentation

4.22.1.1 MODULE_NAME_install ()

Definition at line 4 of file template.php.

References get_entry(), ListAdd(), module_installed(), set_entry(), and set_module_info().

4.22.1.2 MODULE_NAME_some_hook ()

Definition at line 35 of file template.php.

References get_module_info().

4.22.1.3 MODULE_NAME_uninstall ($ *preserve_data*)

Definition at line 23 of file template.php.

References delete_module(), get_entry(), ListDel(), and set_entry().

Chapter 5

modphpcms Page Documentation

5.1 Todo List

File base_page.php This code is not really modular - needs fixing.

Member textToXHTML(&$text,$allowIMG,$NoTags=FALSE) Define where XHTML checking should happen - probably on submitting a page.

Index

activate.inc.php, 7
    style_default_activate, 7
add_field
    db_mysql.php, 16

base_page.inc.php, 8
    Ibase_page_doShowData, 8
    Ibase_page_getColSpan, 8
    Ibase_page_getRowSpan, 8
base_page.php, 10
    base_page_install, 10
    base_page_uninstall, 10
    get_page, 11
    php, 11
base_page_install
    base_page.php, 10
base_page_uninstall
    base_page.php, 10
basic_page.inc.php, 12
    basic_page_DoSummary, 12
    Ibasic_page_cmpID, 12
basic_page.php, 13
    basic_page_content, 13
    basic_page_install, 13
    basic_page_uninstall, 13
    php, 13
basic_page_content
    basic_page.php, 13
basic_page_DoSummary
    basic_page.inc.php, 12
basic_page_install
    basic_page.php, 13
basic_page_uninstall
    basic_page.php, 13

CallHooks
    modfuncs.inc.php, 25
config.inc.php, 14
copyright.php, 15
    copyright_at_bottom, 15
    copyright_install, 15
    copyright_uninstall, 15
copyright_at_bottom
    copyright.php, 15
copyright_install
    copyright.php, 15
copyright_uninstall
    copyright.php, 15
create_entry_table
    db_mysql.php, 16

db_mysql.php, 16
    add_field, 16
    create_entry_table, 16
    delete_entry, 16
    delete_module, 16
    drop_field, 16
    drop_table, 17
    get_array, 17
    get_array2, 17
    get_entry, 17
    get_field, 17
    get_field2, 17
    get_module_info, 17
    get_module_list, 18
    get_reccount, 18
    optimize_table, 18
    set_entry, 18
    set_field, 18
    set_module_info, 18
dbcleanup.php, 19
    dbcleanup_install, 19
    dbcleanup_page_sent, 19
    dbcleanup_uninstall, 19
dbcleanup_install
    dbcleanup.php, 19
dbcleanup_page_sent
    dbcleanup.php, 19
dbcleanup_uninstall
    dbcleanup.php, 19
delete_entry
    db_mysql.php, 16
delete_module
    db_mysql.php, 16
drop_field
    db_mysql.php, 16
drop_table
    db_mysql.php, 17

get_array

db_mysql.php, 17
get_array2
db_mysql.php, 17
get_entry
db_mysql.php, 17
get_field
db_mysql.php, 17
get_field2
db_mysql.php, 17
get_module_info
db_mysql.php, 17
get_module_list
db_mysql.php, 18
get_option
modfuncs.inc.php, 26
get_page
base_page.php, 11
get_reccount
db_mysql.php, 18
GetColor
secureimage.php, 31

HideImage
secureimage.php, 31
hidelevel
secureimage.php, 31
htmlparse.inc.php, 20
Iparse_markup, 20
RemoveHTML, 20
textToXHTML, 21

Ibase_page_doShowData
base_page.inc.php, 8
Ibase_page_getColSpan
base_page.inc.php, 8
Ibase_page_getRowSpan
base_page.inc.php, 8
Ibasic_page_cmpID
basic_page.inc.php, 12
Ilogo_doLogo
logo.php, 22
Iparse_markup
htmlparse.inc.php, 20
is_standard_page
modfuncs.inc.php, 26
Istats_getCount
stats.inc.php, 33
Istats_reallyIE
stats.inc.php, 33
Istats_totalCount
stats.inc.php, 33
Istats_UIRH
stats.inc.php, 33
ListAdd
modfuncs.inc.php, 26
ListDel
modfuncs.inc.php, 26
logo.php, 22
Ilogo_doLogo, 22
logo_bl_cell, 22
logo_br_cell, 22
logo_install, 22
logo_tl_cell, 22
logo_tr_cell, 22
logo_uninstall, 22
logo_bl_cell
logo.php, 22
logo_br_cell
logo.php, 22
logo_install
logo.php, 22
logo_tl_cell
logo.php, 22
logo_tr_cell
logo.php, 22
logo_uninstall
logo.php, 22

MakeImage
secureimage.php, 31
meta_generator.php, 24
meta_generator_in_head, 24
meta_generator_install, 24
meta_generator_uninstall, 24
meta_generator_in_head
meta_generator.php, 24
meta_generator_install
meta_generator.php, 24
meta_generator_uninstall
meta_generator.php, 24
modfuncs.inc.php, 25
CallHooks, 25
get_option, 26
is_standard_page, 26
ListAdd, 26
ListDel, 26
module_installed, 27
set_option, 27
module_installed
modfuncs.inc.php, 27
MODULE_NAME_install
template.php, 37
MODULE_NAME_some_hook
template.php, 37
MODULE_NAME_uninstall
template.php, 37

optimize_table
db_mysql.php, 18
outimg
secureimage.php, 31

page.php, 28
php, 28
pageend.inc.php, 29
pagestart.inc.php, 30
php
base_page.php, 11
basic_page.php, 13
page.php, 28
stats.php, 34
style.php, 36

RemoveHTML
htmlparse.inc.php, 20

secureimage.php, 31
GetColor, 31
HideImage, 31
hidelevel, 31
MakeImage, 31
outimg, 31
text, 31
set_entry
db_mysql.php, 18
set_field
db_mysql.php, 18
set_module_info
db_mysql.php, 18
set_option
modfuncs.inc.php, 27
stats.inc.php, 33
Istats_getCount, 33
Istats_reallyIE, 33
Istats_totalCount, 33
Istats_UIRH, 33
stats.php, 34
php, 34
stats_install, 34
stats_on_request, 34
stats_tr_cell, 34
stats_uninstall, 34
stats_install
stats.php, 34
stats_on_request
stats.php, 34
stats_text.php, 35
stats_text_DoStats, 35
stats_text_install, 35
stats_text_uninstall, 35
stats_text_DoStats
stats_text.php, 35
stats_text_install
stats_text.php, 35
stats_text_uninstall
stats_text.php, 35
stats_tr_cell
stats.php, 34
stats_uninstall
stats.php, 34
style.php, 36
php, 36
style_default_activate
activate.inc.php, 7

template.php, 37
MODULE_NAME_install, 37
MODULE_NAME_some_hook, 37
MODULE_NAME_uninstall, 37
text
secureimage.php, 31
textToXHTML
htmlparse.inc.php, 21